

Documentation for writing to InfluxDB from RaspberryPi 4 post receiving data from ESP32 via BLE

ESP32:

//Sending data from ESP32 to RPi4 - Air Quality monitoring sensors used

```
#include "BluetoothSerial.h"
#include<BLEDevice.h>
#include<DHT.h>
BluetoothSerial SerialBT;
#define DHTPIN 4
#define DHTTYPE DHT11
#define mq 34
DHT dht(DHTPIN, DHTTYPE);
void setup() {
  Serial.begin(115200);
  dht.begin();
  pinMode(mq, INPUT);
  SerialBT.begin("ESP32-BT-Server"); // Name of your Bluetooth device
  Serial.println("Bluetooth Started! Ready to pair...");
  if (SerialBT.available()) {
    String data = SerialBT.readStringUntil('\n'); // Read until newline
    Serial.print("Received from Raspberry Pi:");
    Serial.println(data);
  }
}

void loop() {
  float temp = dht.readTemperature();
  float hum = dht.readHumidity();
  float gas=analogRead(mq);

  Serial.print("Temperature sensor:");
  Serial.println(temp);

  Serial.print("Humidity sensor:");
  Serial.println(hum);
  char data[64];
  snprintf(data,sizeof(data),"%f,%f,%f",temp,hum,gas);

  SerialBT.print(data);
  Serial.print("Gas sensor:");
  Serial.println(gas);
  delay(2000);
}
```

RaspberryPi 4:

(i)Setting up InfluxDB:

//Installing and adding the InfluxDB repository

01 wget -qO- https://repos.influxdata.com/influxdb.key | sudo apt-key add-

02 echo "deb https://repos.influxdata.com/debian stable main" sudo
tee/etc/apt/sources.list.d/

//Update and install influxDB

03 sudo apt-get update

04 sudo apt-get install influxdb

//Start and enable influxdb

04 sudo systemctl start influxdb

05 sudo systemctl enable influxdb

//Verify if the influxdb is in active running state

06 sudo systemctl status influxdb

//Configuring influxdb

//open influxdb

07 influx

//Creating a database

08 CREATE DATABASE database_name

//Creating user for the above database

09 CREATE USER "my_user" WITH PASSWORD 'my_password' WITH ALL PRIVILEGES

//Grant write permissions to the user

10 GRANT WRITE ON database_name TO "my_user"

//exit the influxdb shell

11 exit

//Install the python libraries for influxdb-client

12 sudo pip3 install influxdb-client

Post executing these commands in the terminal, run your "xyz.py" script

(ii)RPi 4 Code:

import bluetooth

from influxdb import InfluxDBClient

import time

InfluxDB 1.x Configuration

INFLUX_HOST = "localhost" # Change if InfluxDB is on another system

INFLUX_PORT = 8086

```

INFLUX_DB = "database2" # Your database name
MEASUREMENT = "sensor_data" # Table name
# Initialize InfluxDB Client
client = InfluxDBClient(host=INFLUX_HOST, port=INFLUX_PORT,
database=INFLUX_DB)
# Find the Bluetooth address of ESP32
def find_esp32_address(target_name="ESP32-BT-Server"):
    print("Searching for ESP32 Bluetooth device...")
    nearby_devices = bluetooth.discover_devices(duration=8, lookup_names=True,
flush_cache=True, lookup_class=False)
    for addr, name in nearby_devices:
        print(f"Found: {name} - {addr}")
        if name == target_name:
            return addr
    return None

def main():
    esp32_address = find_esp32_address()
    if esp32_address is None:
        print("ESP32 not found. Ensure it is advertising.")
        return

    print(f"ESP32 address: {esp32_address}")

    try:
        # Create an RFCOMM socket
        sock = bluetooth.BluetoothSocket(bluetooth.RFCOMM)
        sock.connect((esp32_address, 1)) # Port 1 is the default for Bluetooth Serial
        sock.settimeout(10) # Set timeout to avoid blocking
        print("Connected to ESP32!")

```

while True:

try:

```
data = sock.recv(1024).decode('utf-8').strip()
print(f"Received from ESP32: {data}")
```

```
temp_str, hum_str, gas_str = data.split(',')
temp = float(temp_str)
humidity = float(hum_str)
gas = float(gas_str)
```

Get timestamp

```
timestamp = int(time.time() * 1e9)
```

Prepare JSON payload for InfluxDB

```
json_body = [
    {
        "measurement": MEASUREMENT,
        "time": timestamp,
        "fields": {
            "temperature": temp,
            "humidity": humidity,
            "gas": gas,
        }
    }
]
client.write_points(json_body)
print(f"Written: Timestamp={timestamp}")
time.sleep(2)
```

except bluetooth.btcommon.BlutetoothError as e:

```

        print(f"Error receiving data: {e}")
        break

except bluetooth.btcommon.BlutetoothError as e:
    print(f"Bluetooth error: {e}")

except KeyboardInterrupt:
    print("Exiting...")

finally:
    if 'sock' in locals() and sock is not None:
        sock.close()
        print("Bluetooth connection closed.")

if __name__ == "__main__":
    main()

```

(iii) Reading from InfluxDB using SQL queries:

//Execute this code in RPi system

```

from influxdb import InfluxDBClient

# InfluxDB 1.x Configuration

INFLUX_HOST = "localhost" # Change if InfluxDB is on another system

INFLUX_PORT = 8086

INFLUX_DB = "database2" # Your database name

MEASUREMENT = "sensor_data" # Your measurement (table) name

# Initialize InfluxDB Client

client = InfluxDBClient(host=INFLUX_HOST, port=INFLUX_PORT,
database=INFLUX_DB)

```

```
# Query data from InfluxDB
```

```
query = f'SELECT * FROM {MEASUREMENT} ORDER BY time DESC LIMIT 10'
```

```
# Fetch last 10 entries
```

```
result = client.query(query)
```

```
# Extract and print data
```

```
points = list(result.get_points())
```

```
if points:
```

```
    print("Latest Sensor Data:")
```

```
    for point in points:
```

```
        print(f"Time: {point['time']}, Temperature: {point['temperature']}, Humidity:  
{point['humidity']}, MQ: {point['gas']}") # modified line
```

```
else:
```

```
    print("No data found in InfluxDB!")
```

```
# Close InfluxDB connection
```

```
client.close()
```